


Morning Call



Placemat Box



Napkin Box



Coaster Box



Coaster #1




Coaster #2



Napkin



Placemat - Black Version



Placemat - Tomato Version

Fabric and projects designed by Hoodie's Collection
Instructions by Jean Ann Wright



TM

Morning Call

Fabric and projects designed by Hoodie's Collection Instructions by Jean Ann Wright

Skill level: Intermediate

General Instructions and Supplies:

Black and ivory sewing thread

Steam-a-seam 1/4" fusible web for placemats and coasters

Thermal heat reducing batting for coasters, potholder, oven mitt and kettle mat

Timtex interfacing for fabric boxes

Water soluble fabric marking pen

* Seam allowances for all projects are 1/4" unless otherwise indicated

Fabric Boxes

Placemat Box: 8" x 8", sides 3" high

Napkin Box: 7" x 7", sides 2 1/2" high

Coaster Box: 4 1/2" x 4 1/2", sides 2" high

Box Fabric Requirements:

Fabric A	1/3 yard	5287 TOMATO
Fabric B	1/2 yard	5292 APPLE
Fabric C	1/2 yard	5292 OLIVE
Fabric D	1/2 yard	5291 OLIVE
Fabric E	1/2 yard	5287 EGG
Fabric F	1/3 yard	5289 APPLE
Fabric G	1/3 yard	5296 BLACK

Fabric Boxes Cutting

Fabric A	Six 1 1/4" x wof strips for ties (2 pieces for each box)
Fabric B	One 14 3/4" x 14 3/4" square for placemat box
Fabric C	One 14 3/4" x 14 3/4" square for placemat box
Fabric D	One 12 3/4" x 12 3/4" square for napkin box
Fabric E	One 12 3/4" x 12 3/4" square for napkin box
Fabric F	One 9 1/4" x 9 1/4" square for coaster box
Fabric G	One 9 1/4" x 9 1/4" square for coaster box
Timtex	One 8" x 8" square for placemat box bottom Four 3" x 8" rectangles for placemat box sides One 7" x 7" square for napkin box bottom

Four 2 1/2" x 7" rectangles for napkin box sides
One 4 1/2" x 4 1/2" square for coaster box bottom
Four 2" x 4 1/2" rectangles for coaster box sides

Fabric Boxes Sewing

- For each of the boxes, stack the two fabric squares with right sides together. Measure and mark 3 5/8" in from opposite corners on one side for the placemat box; 3 1/8" in from opposite corners on one side of the napkin box; and 2 5/8" in from opposite corners on one side on the coaster box.
- Start stitching at the marked position to the corner, turn, stitch down the side, across the bottom and up the other side. Turn again and stitch to the mark on the beginning side leaving an opening between the marks.
- Turn each box right sides out and press seam lines crisply taking care to push each corner out to a sharp right angle.
- Using a water-soluble pen mark each of the sides of the fabric square using the same measurement on the side for the box opening. Draw the seam lines from one side to the opposite sides on each box square.
- Tuck each of the 4 rectangles for each box into the inside of the squares and position firmly against the seam line and between the two stitching lines drawn with the pen. Pin in place. Tuck the square for each box into the inside of the box taking care to have it positioned in the center of the four marked seam lines. Leave a space of about 1/8" between the Timtex squares and rectangles to stitch the Timtex in place. Stitch from one side of the box to the opposite side of the box to hold the Timtex pieces. Take care not to stitch through the Timtex.
- Sew the six Fabric A strips in half lengthwise with right sides together and press the fold line. Sew together. Trim the seam allowance to 1/8". Turn the strips right sides out and cut each strip into 4 equal pieces to make the ribbon ties for the boxes.
- Using a stitch ripper make a 1/2" opening on the inside of the stitching holding the Timtex rectangles in place. Tuck a Fabric A ribbon into each of the openings and pin in place. Tie a single tight knot at the loose end of each fabric ribbon.
- Turn the seams on the open side of the box towards the inside of the box, covering the Timtex with one of the seam allowances. Press and match the folded seam lines in place. Pin opening together. Topstitch around the entire outside of the box to finish. The topstitching will hold the fabric ribbons in place and sew the opening on the turned side of the box together.

Napkins

Size: 15" x 15"

Napkins Fabric Requirements:

Fabric A	1 yard	5291 OLIVE
----------	--------	------------

Napkins Cutting

Fabric A	Four 16" x 16" squares
----------	------------------------

Napkins Sewing

- Sew a narrow hem all around the outside edges of each of the Fabric A napkins to finish raw edges.

Placemats

Size: 19" x 13 1/2"

Fabric Requirements (for 2 placemats in each colorway)

	Tomato Version
Fabric A	1/2 yard
Fabric B	1/8 yard
Fabric C	1/2 yard
Fabric D	1/2 yard
Fabric E	1/8 yard

	Black Version
Fabric A	1/2 yard
Fabric B	1/8 yard
Fabric C	1/2 yard
Fabric D	1/2 yard
Fabric E	1/8 yard

Cutting directions for single placemat

Fabric A	Two 4" x 13 1/2" vertical rectangles
Fabric B	Two 4 1/4" squares cut in half on diagonal once to make 4 triangles
Fabric C	One 15 1/2" x 21" rectangle for back of placemat
Fabric D	One 12 1/2" x 13 1/2" vertical rectangle
Fabric E	One 1" x width of fabric strips, recut into two 14" pieces and four 6 1/2" pieces

Placemats Sewing

- Fold the Fabric E strips in half lengthwise with wrong sides together. Press the fold line. Using the 4 short strips, match raw, folded edges of strips to raw edge of long side of the 4 fabric B triangles. Sew in place then turn all raw edges to the back of each triangle and press. Set triangles aside.
- Position the 2 long Fabric E strips on the top of the Fabric D rectangle on each side with raw edges together. Pin the Fabric A piece on top of each, right sides together. Stitch through all layers on each side then fold the fabric A pieces out and press the seam lines.
- Pin the triangles finished in step 1 to each corner. Center the placemat on top of the backing piece with wrong sides together. Fold the raw edges of the placemat back to the front of the placemat, turn the raw edges under with a scant 1/2" of the fabric backing showing on the placemat front. Fuse in place using the Steam-a-seam fusible web. Topstitch around all four sides to finish.

Coasters

Size: 4" x 4"

Fabric requirements (for 4 coasters in each colorway)

	Coaster Set One
Fabric A	1/4 yard
Fabric B	1/4 yard
Fabric C	1/4 yard

	Coaster Set Two
Fabric A	1/4 yard
Fabric B	1/4 yard
Fabric C	1/4 yard


Cutting directions for coasters in sets of two

Fabric A	One 4 3/4" x 4 3/4" square, cut in half on diagonal twice for four triangles
Fabric B	One 4 3/4" x 4 3/4" square, cut in half on diagonal twice for four triangles
Fabric C	Two 4 1/2" squares for coaster backing

Thermal heat reducing batting – cut one 4" squares for each coaster.

Sewing Coasters

- Sew the Fabric A triangles to the Fabric B triangles. Sew the sets of triangles together.
- Position the finished patchwork on top of the thermal batting then center on top of the fabric backing. Quilt the layers together making an X across the seam lines.
- Fold the raw edges of the coaster back to the front of the placemat, turn the raw edges under with a generous 1/4" of the fabric backing showing on the placemat front. Fuse in place using the Steam-a-seam fusible web. Topstitch around all four sides to finish.



While all possible care has been taken to ensure the accuracy of this pattern, we are not responsible for printing errors or the way in which individual work varies.



© 2008 Blank Quilting • All rights reserved

2 Bridge Street, Suite 220, Irvington, NY 10533 • Toll Free: 1-888-442-5265 • Fax: 914-478-4278 • www.BlankQuilting.com